### Modes of Operation

- block ciphers encrypt fixed size blocks
- eg. DES encrypts 64-bit blocks, with 56-bit key
- need way to use in practise, given usually have arbitrary amount of information to encrypt
- four were defined for DES in ANSI standard
  ANSI X3.106-1983 Modes of Use
- subsequently now have 5 for DES and AES
- have block and stream modes

#### Electronic Codebook Book (ECB)

- message is broken into independent blocks which are encrypted
- each block is a value which is substituted, like a codebook, hence name
- each block is encoded independently of the other blocks

 $C_{i} = DES_{K1}$  (P<sub>i</sub>)

uses: secure transmission of single values

#### Electronic Codebook Book (ECB)



#### Advantages and Limitations of ECB

- repetitions in message may show in ciphertext
  - if aligned with message block
  - particularly with data such graphics
  - or with messages that change very little, which become a code-book analysis problem
- weakness due to encrypted message blocks being independent
- main use is sending a few blocks of data

# Cipher Block Chaining (CBC)

- message is broken into blocks
- but these are linked together in the encryption operation
- each previous cipher blocks is chained with current plaintext block, hence name
- use Initial Vector (IV) to start process

$$C_{i} = DES_{K1} (P_{i} XOR C_{i-1})$$
  
 $C_{-1} = IV$ 

uses: bulk data encryption, authentication

### Cipher Block Chaining (CBC)



#### Advantages and Limitations of CBC

- each ciphertext block depends on **all** message blocks
- thus a change in the message affects all ciphertext blocks after the change as well as the original block
- need Initial Value (IV) known to sender & receiver
  - however if IV is sent in the clear, an attacker can change bits of the first block, and change IV to compensate
  - hence either IV must be a fixed value (as in EFTPOS) or it must be sent encrypted in ECB mode before rest of message
- at end of message, handle possible last short block
  - by padding either with known non-data value (eg nulls)
  - or pad last block with count of pad size
    - eg. [ b1 b2 b3 0 0 0 5] <- 3 data bytes, then 5 bytes pad+count

### Cipher FeedBack (CFB)

- message is treated as a stream of bits
- added to the output of the block cipher
- result is feed back for next stage (hence name)
- standard allows any number of bit (1,8 or 64 or whatever) to be feed back

- denoted CFB-1, CFB-8, CFB-64 etc

- is most efficient to use all 64 bits (CFB-64)
  C<sub>i</sub> = P<sub>i</sub> XOR DES<sub>K1</sub> (C<sub>i-1</sub>)
  C<sub>-1</sub> = IV
- uses: stream data encryption, authentication

#### Cipher FeedBack (CFB)



#### Advantages and Limitations of CFB

- appropriate when data arrives in bits/bytes
- most common stream mode
- limitation is need to stall while do block encryption after every n-bits
- note that the block cipher is used in encryption mode at both ends
- errors propagate for several blocks after the error

## Output FeedBack (OFB)

- message is treated as a stream of bits
- output of cipher is added to message
- output is then feed back (hence name)
- feedback is independent of message
- can be computed in advance

$$C_i = P_i XOR O_i$$

$$O_i = DES_{K1} (O_{i-1})$$

 $O_{-1} = IV$ 

• uses: stream encryption over noisy channels

#### Output FeedBack (OFB)



#### Advantages and Limitations of OFB

- used when error feedback a problem or where need to encryptions before message is available
- superficially similar to CFB
- but feedback is from the output of cipher and is independent of message
- a variation of a Vernam cipher
  - hence must never reuse the same sequence (key+IV)
- sender and receiver must remain in sync, and some recovery method is needed to ensure this occurs
- originally specified with m-bit feedback in the standards
- subsequent research has shown that only OFB-64 should ever be used

# Counter (CTR)

- a "new" mode, though proposed early on
- similar to OFB but encrypts counter value rather than any feedback value
- must have a different key & counter value for every plaintext block (never reused)
  - $C_i = P_i XOR O_i$
  - $O_{i} = DES_{K1} (i)$
- uses: high-speed network encryptions

### Counter (CTR)



#### Advantages and Limitations of CTR

- efficiency
  - can do parallel encryptions
  - in advance of need
  - good for bursty high speed links
- random access to encrypted data blocks
- provable security (good as other modes)
- but must ensure never reuse key/counter values, otherwise could break (cf OFB)